

## Scale Fingerings

### I. Scales beginning on white keys.

R.H. 123 1234 123 1234 5

L.H. 5 4321 321 4321 321

"C Major fingering" (given above) is used for all major and minor scales beginning on white keys with only two exceptions:

R.H. F 1234 123 1234 123 4

L.H. B 4 321 4321 321 4321

### II. Scales beginning on black keys.

#### Major

R.H. Fourth finger is always on B-flat

Two black keys -- use 23

Three black keys -- use 234

L.H. 321 4321 321 4321 2 on all

except F# (G-flat) -- 4321 321 4321 321 2

#### Minor

R.H. f#, c#, g# (a-flat) -- 34 123 1234 123 123

d# (e-flat) -- 3 1234 123 1234 123

a# (b-flat) -- 4 123 1234 123 1234

L.H. f#, c#, g# (a-flat) -- major fingering

d# (e-flat) -- 21 4321 321 4321 32

a# (b-flat) -- 21 321 4321 321 432